

# INSTALLATION MANUAL

## DL-1060/2060 CONTROL SOFTWARE

DL-TOOL

DL-LINK

SC-TOOL



## SUMMARY

Texio software provides a convenient way for your measurements. DL-Tool & DL-Link is used to communicate with DL-1060 or DL-2060 from a PC. DL-Tool is a similar virtual oscilloscope software, which can monitor the DUT with scope display style. DL-Link is used to collect measurement data in Microsoft Excel or Word and analyze it with charts. SC-TOOL provides switching and scanning up to 10 (or 20) channels of input signals for DL-2060 with the optional scanner card. You can use this software as a data acquisition system.

### [System requirements]

OS : Windows 2000 / XP/ VISTA / 7  
Microsoft Word & Excel : Office2000 / 2003 / XP / 2007 /2010  
Interface : USB(1.0, 2.0), GPIB

### [List of files]

CD includes executable files as following:

Name	Description	Software
DL-1060/2060 driver (Required)	Driver for DL-1060/2060	DL-1060_2060_***.exe
DL-TOOL	Control software for DL-1060/2060	
DL-LINK	For Microsoft Word & Excel	
SC-TOOL	Control software for Scanner-Card	SC-TOOL_***.exe
Runtime for NI-VISA	Driver for NI-VISA	Visa502runtime.exe

※ **Please be sure to install NI-VISA before executing DL-1060/2060.**

※ **DL-LINK is installed as “Add-in” function for Macro for Microsoft Word and Excel.**

**Select the function (enable or not) by clicking “Add-in” in “Tool” menu of Word and Excel.**

Please download from our HP (<http://www.texio.co.jp>) or from HP of NI (<http://www.ni.com/visa>) for latest version of each software.

### [Regarding the registered trademark]

Windows, Windows 2000 / XP/ VISTA / 7, Microsoft Word/ Excel is the registered trademark of Microsoft Corporation in the USA and other countries

NI-VISA is the registered trademark of National instruments Corp.

## Software Installation

### STEP1 (Driver install of NI-VISA)

Insert the CD into the CD-ROM drive of your computer. The CD should start automatically, and then the following window will appear. Click "NI-VISA Driver Software" then follow the instructions in the installation wizard

**TEXIO**

PRODUCTS

6 1/2 Digital Multimeter

1. USBTMC Driver  
**NI-VISA Driver Software**


2. Applications  
[Software for DL-1060/2060 \(DL-Tool/Link\)](#)  
[Software for Scanner-Card \(SC-TOOL\)](#)  
[Installation Manual \(Japanese\)](#)  
[Installation Manual \(English\)](#)

3. Documents  
[DL-2060 Instruction Manual \(Japanese\)](#)  
[DL-2060 Instruction Manual \(English\)](#)  
[DL-Tool Instruction Manual \(Japanese\)](#)  
[SC-Tool Instruction Manual \(Japanese\)](#)

All manuals are PDF file type data,  
Adobe Acrobat Reader required.

**TEXIO TECHNOLOGY CORPORATION**  
<http://www.texio.co.jp>

If the menu does not start, click "main.htm" file direct.




STEP2 (Application install of DL-1060/2060)

Depending on your needs, install the application software.

Follow the instructions in the installation wizard.


(For example, DL-TOOL/Link)



**TEXIO**

PRODUCTS

6 1/2 Digital Multimeter



1. USBTMC Driver  
[NI-VISA Driver Software](#)
2. Applications  
[Software for DL-1060/2060 \(DL-Tool/Link\)](#)  
[Software for Scanner-Card \(SC-TOOL\)](#)  
[Installation Manual \(Japanese\)](#)  
[Installation Manual \(English\)](#)
3. Documents  
[DL-2060 Instruction Manual \(Japanese\)](#)  
[DL-2060 Instruction Manual \(English\)](#)  
[DL-Tool Instruction Manual \(Japanese\)](#)  
[SC-Tool Instruction Manual \(Japanese\)](#)

All manuals are PDF file type data,  
Adobe Acrobat Reader required.

**TEXIO TECHNOLOGY CORPORATION**  
<http://www.texio.co.jp>

STEP3: Click "Next".



**TEXIO DL-1060/2060 Software Setup**

Welcome to the TEXIO DL-1060/2060 Software Setup Wizard


This wizard will guide you through the installation of TEXIO DL-1060/2060 Software.

It is recommended that you close all other applications before starting Setup. This will make it possible to update relevant system files without having to reboot your computer.


Click Next to continue.

**Next >** Cancel

STEP4: Click "Next" selecting software to install.



STEP5: Install will start by click "Install" indicating the folder to install.





**TEXIO TECHNOLOGY CORPORATION**

7F Towa Fudosan Shin Yokohama Bild.

2-18-13, Shin Yokohama, Kohoku-ku, Yokohama, Kanagawa, 222-0033 Japan

<http://www.texio.co.jp/>

---